

ChatWork Plugin

Summary

This Plugin will notify the ChatWork any message.

Plugin Information
View ChatWork on the plugin site for more information.

XXXXXXXXXXXXXXXXXXXXXXXXXXXX

Table of content

- Summary
 - Table of content
- Usage
 - Global Configuration
 - Job Configuration
- Changelog
 - Version 1.0.8 (Jan 27, 2017)
 - Version 1.0.6 (Dec 1, 2016)
 - Version 1.0.5 (Mar 23, 2016)
 - Version 1.0.4 (Nov 11, 2015)
 - Version 1.0.3 (Oct 8, 2015)
 - Version 1.0.2 (Sep 25, 2015)
 - Version 1.0.1 (Sep 25, 2015)
 - Version 1.0.0 (Mar 8, 2015)
 - NOTE
 - Version 0.6.2 (Jan 22, 2015)
 - Version 0.6.1 (Jan 14, 2015)

Usage

Global Configuration

Chatwork Plugin	
API Key	<input type="text" value="XXXXXXXXXXXXXXXXXXXXXXXXXXXX"/>
Proxy server	<input type="text" value="NOPROXY"/> Set your Chatwork API Key If you don't want to use proxy, set "NOPROXY" or blank
Proxy port	<input type="text"/> Set your Proxy server
Global Success message	<input type="text" value="[info][title]\${JOB_NAME} \${BUILD_DISPLAY_NAME} (\${GIT_BRANCH})[/title]build is \${BUILD_RESULT} \${BUILD_URL}[/info]"/>
Global Failure message	<input type="text" value="[info][title]\${JOB_NAME} \${BUILD_DISPLAY_NAME} (\${GIT_BRANCH})[/title]build is \${BUILD_RESULT}"/>
Global Unstable message	<input type="text" value="[info][title]\${JOB_NAME} \${BUILD_DISPLAY_NAME} (\${GIT_BRANCH})[/title]build is \${BUILD_RESULT}"/>
Global Not built message	<input type="text" value="[info][title]\${JOB_NAME} \${BUILD_DISPLAY_NAME} (\${GIT_BRANCH})[/title]build is \${BUILD_RESULT}"/>
Global Aborted message	<input type="text" value="[info][title]\${JOB_NAME} \${BUILD_DISPLAY_NAME} (\${GIT_BRANCH})[/title]build is \${BUILD_RESULT}"/>

Job Configuration

Notify the ChatWork

Choose room you want to notice

all direct group my

Success message

If 'Success message' is blank, used 'Global Success message'

notify on build success

Failure message

If 'Failure message' is blank, used 'Global Failure message'

notify on build failure

Unstable message

If 'Unstable message' is blank, used 'Global Unstable message'

- **Success message** , **Failure message** , **Unstable message** , **Not built message** , **Aborted message**
 - If message is empty, used Global message
 - emoticon
 - chatwork tags
- **Default message** is supported some variables.

example

- build variables (ex. `$JOB_NAME` , `$BUILD_URL`)
- environment variables (ex. `$PATH` , `$JAVA_HOME`)
- `$BUILD_RESULT` (ex. `SUCCESS` , `FAILED`)

Changelog

Details <https://github.com/jenkinsci/chatwork-plugin/blob/master/CHANGELOG.md>

Version 1.0.8 (Jan 27, 2017)

- Update API version (v2)

Version 1.0.6 (Dec 1, 2016)

- Fix NullPointerException when contains canceled user

Version 1.0.5 (Mar 23, 2016)

- Sanitize special char in room name

Version 1.0.4 (Nov 11, 2015)

- Bugfix causing null value exception when received Github `payload` json (neither PullRequest nor compare)

Version 1.0.3 (Oct 8, 2015)

- Bugfix multibyte garbled

Version 1.0.2 (Sep 25, 2015)

- Remove legacy help

Version 1.0.1 (Sep 25, 2015)

- Add room selection pulldown instead of textbox

Version 1.0.0 (Mar 8, 2015)

- Add build result pattern messages
- Add global messages

NOTE

Default message (below v0.6.2) is removed. If upgrade from v0.x to 1.0.0+, **Default message** is copied to **Success message**, **Failure message**, **Unstable message**, **Not built message** and **Aborted message**

Version 0.6.2 (Jan 22, 2015)

- Support variable to room id

Version 0.6.1 (Jan 14, 2015)

- Bugfix: Failed to serialize