

Spark Plugin

Plugin Information

View Cisco Spark [on the plugin site](#) for more information.

This plugin allow you to post customized message to Cisco spark room. **Introduce**

The content which be published to Cisco spark room can contain customized content which supports environment vars and some customized vars, such as BUILD_STATUS. if the content contain DEFAULT_CONTENT,, it will be replaced with BUILD_STATUS-JOB_NAME:BUILD_NUMBER-JOB_URL.

Any issues you can contact with author: fujian1115@gmail.com or [Sina microblog](#).

All versions can check the [Maven Repo](#).

Setup

The Cisco spark plugin depends on the [Token-Macro-Plugin](#),you should setup the plugin before using Cisco spark plugin.

Usage


<input checked="" type="checkbox"/> Cisco Spark Plugin 1.0.1 卸载	
This plugin allows you to publish content to Cisco spark room.	
Cisco Spark Setting	
Cisco Spark Room List :	Name <input type="text" value="dev-group"/>
	Room ID <input type="text" value="ae43e420-d236-11e5-88f7-3b8564d072cc"/>
	Bearer Token <input type="text" value="....."/>
	删除
	增加

FAQ:

1 How to get room ID:

1.1 Login Into: <https://web.ciscospark.com/>

1.2 Click the room you wanted to post message, then you will see the room ID on URL.



2 How to get token:

use one robot:

1. access <https://developer.ciscospark.com/add-bot.html#> to add one robot and use its "Access token"

Bot's Access Token

Non-expiring (good for 100 years) access token for your bot.

MjRINDU0NTctNjcyOS00ZGM1LTNmZGEtZDk1NTBINzdjMjlxMTBIYzY4MTYtME

[Copy](#)

The Secret will only be shown once so please copy and keep it safe! You can always regenerate it, but you will not see this one again.


2. invite the robot to your room
the token will always be valid.

or:



use your token:

1. login <https://developer.ciscospark.com>

2. click right top position for owner's image to copy "My Access Token"



3 Snapshots



Version History

Version 1.1.1 (September 16, 2017)

1 add new method to get token: add one robot.

1.1 access <https://developer.ciscospark.com/add-bot.html#> to add one robot and use its "Access token".
1.2 invite the robot to your room
the token will always be valid.

Version 1.1.0 (September 16, 2017)

1 add pipeline support. (Thanks to <https://github.com/asherlporetz>)

2 fix the issue: <https://github.com/jiafu1115/spark-plugin/issues/1>. can custome notify content's prefix message

3 add help document for how to get room id

Version 1.0.0-SNAPSHOT (May19, 2016)

- Initial release